

# 1 多租户体系结构


多租户是Oracle 12c的新特性，该特性能够让您在多租户容器数据库（CDB）中创建和维护多个可插拔数据库（PDB）。

多租户容器数据库（CDB）被定义为可以容纳一个或多个插件数据库的数据库，容器被定义为存在于CDB中数据文件和元数据的集合，可插拔数据库是一种特殊类型的容器，它可以通过克隆其他数据库很容易的进行创建，如果需要，可插拔数据库也可以从一个CDB迁移到另一个CDB中。

每个CDB是由一个根容器（CDB\$ROOT）、一个种子容器（PDB\$SEED）和0个、一个或多个可插拔数据库组成，其中，根容器包含一组主数据文件和元数据，种子容器是用于创建其它可插拔数据库，可插拔数据库包括它自己的数据文件和应用程序对象（用户、表，索引等）。12c之前的数据库都是非容器数据库（non-CDB）。

多租户特性需要额外收费。

下图展示了可插拔数据库的体系结构：



## 2 创建容器数据库CDB

### 2.1 使用DBCA创建

参照DBCA建库。

### 2.2 使用Create Database语句创建

1) 指定实例SID

```
[oracle@strong ~]$ export ORACLE_SID=db01
```

## 2) 设置环境变量

```
[oracle@strong ~]$ echo $ORACLE_SID
db01
[oracle@strong ~]$ echo $ORACLE_HOME
/u01/app/oracle/product/12.2.0/dbhome_1
```

## 3) 创建密码文件

```
[oracle@strong ~]$ orapwd file='/u01/app/oracle/product/12.2.0/dbhome_1/dbs/orapwdb01'
format=12.2
```

Enter password for SYS:

## 4) 创建文本初始化参数文件

```
[oracle@strong ~]$ vim initdb01.ora
db_name='db01'
memory_target=400M
control_files='/u01/app/oracle/oradata/db01/control01.ctl','/u01/app/oracle/oradata/db01/control02.ctl'
enable_pluggable_database=true
```

## 5) 连接实例db01

```
[oracle@strong ~]$ sqlplus /nolog
```

SQL\*Plus: Release 12.2.0.1.0 Production on Tue Aug 7 13:25:18 2018

Copyright (c) 1982, 2016, Oracle. All rights reserved.

```
SQL> conn / as sysdba
Connected to an idle instance.
```

## 6) 创建服务器参数文件

```
SQL> create spfile from pfile='/home/oracle/initdb01.ora';
```

File created.

## 7) 启动实例

```
SQL> startup nomount
```

ORACLE instance started.

Total System Global Area 419430400 bytes

Fixed Size 8621424 bytes

Variable Size 301990544 bytes

Database Buffers 104857600 bytes

Redo Buffers 3960832 bytes

## 8) 创建目录

```
[oracle@strong ~]$ cd /u01/app/oracle/oradata/
```

```
[oracle@strong oradata]$ mkdir db01
```

```
[oracle@strong oradata]$ cd db01/
```

```
[oracle@strong db01]$ mkdir pdbseed
```

## 9) 创建建库脚本

```
[oracle@strong ~]$ cat db01.sql
```

```
CREATE DATABASE db01
```

```
  USER SYS IDENTIFIED BY "Foxconn168!"
```

```
  USER SYSTEM IDENTIFIED BY "Foxconn168!"
```

```
  LOGFILE GROUP 1 ('/u01/app/oracle/oradata/db01/redo01.log')
```

```
    SIZE 100M BLOCKSIZE 512,
```

```
  GROUP 2 ('/u01/app/oracle/oradata/db01/redo02.log')
```

```
    SIZE 100M BLOCKSIZE 512,
```

```
  GROUP 3 ('/u01/app/oracle/oradata/db01/redo03.log')
```

```
    SIZE 100M BLOCKSIZE 512
```

```
  MAXLOGHISTORY 1
```

```
  MAXLOGFILES 16
```

```
  MAXLOGMEMBERS 3
```

```
  MAXDATAFILES 1024
```

```
  CHARACTER SET AL32UTF8
```

```
  NATIONAL CHARACTER SET AL16UTF16
```

```
  EXTENT MANAGEMENT LOCAL
```

```
  DATAFILE '/u01/app/oracle/oradata/db01/system01.dbf'
```

```
    SIZE 700M REUSE AUTOEXTEND ON NEXT 10240K MAXSIZE UNLIMITED
```

```
  SYSAUX DATAFILE '/u01/app/oracle/oradata/db01/sysaux01.dbf'
```

```
    SIZE 550M REUSE AUTOEXTEND ON NEXT 10240K MAXSIZE UNLIMITED
```

```
  DEFAULT TABLESPACE deftbs
```

```
    DATAFILE '/u01/app/oracle/oradata/db01/deftbs01.dbf'
```

```
    SIZE 500M REUSE AUTOEXTEND ON MAXSIZE UNLIMITED
```

```
  DEFAULT TEMPORARY TABLESPACE tempts1
```

```
    TEMPFILE '/u01/app/oracle/oradata/db01/temp01.dbf'
```

```
SIZE 20M REUSE AUTOEXTEND ON NEXT 640K MAXSIZE UNLIMITED
UNDO TABLESPACE undotbs1
DATAFILE '/u01/app/oracle/oradata/db01/undotbs01.dbf'
SIZE 200M REUSE AUTOEXTEND ON NEXT 5120K MAXSIZE UNLIMITED
ENABLE PLUGGABLE DATABASE
SEED
FILE_NAME_CONVERT = ('/u01/app/oracle/oradata/db01/',
                    '/u01/app/oracle/oradata/db01/pdbseed/')
LOCAL UNDO ON;
```

10) 执行建库脚本

```
SQL> @db01.sql
```

Database created.

创建容器数据库初始化参数enable\_pluggable\_database必须设置为TRUE，除此之外，所需的目录也必须提前创建，否则执行脚本时会出错。

11) 执行脚本

```
SQL> @?/rdbms/admin/catcdb.sql
```

出现以下提示时，在参数1处输入目录，参数2处输入文件名称：

```
SQL> host perl -I &&rdbms_admin &&rdbms_admin_catcdb --logDirectory &&1 --logFilename &&2
```

```
Enter value for 1: /home/oracle
```

```
Enter value for 2: create_cdb.log
```

## 3 管理Root容器

### 3.1 连接Root容器

以SYS用户连接到Root容器可以执行与数据库相关的所有任务，可以通过OS身份验证或网络方式进行连接。

1) OS认证方式

```
[oracle@strong ~]$ sqlplus / as sysdba
```

```
SQL*Plus: Release 12.2.0.1.0 Production on Mon Aug 6 15:52:23 2018
```

```
Copyright (c) 1982, 2016, Oracle. All rights reserved.
```

Connected to:  
Oracle Database 12c Enterprise Edition Release 12.2.0.1.0 - 64bit Production

```
SQL> show user con_id con_name user  
USER is "SYS"
```

```
CON_ID  
-----  
1
```

```
CON_NAME  
-----  
CDB$ROOT  
USER is "SYS"
```

## 2) 网络方式连接

```
[oracle@strong ~]$ sqlplus sys/system@orcl as sysdba
```

```
SQL*Plus: Release 12.2.0.1.0 Production on Mon Aug 6 15:54:54 2018
```

```
Copyright (c) 1982, 2016, Oracle. All rights reserved.
```

Connected to:  
Oracle Database 12c Enterprise Edition Release 12.2.0.1.0 - 64bit Production

```
SQL>
```

## 3.2 展示当前连接的容器信息

### 1) Show命令

```
SQL> show user con_id con_name user  
USER is "SYS"
```

```
CON_ID  
-----  
1
```

```
CON_NAME  
-----  
CDB$ROOT
```

USER is "SYS"

## 2) SQL语句

```
SQL> SELECT sys_context('USERENV','CON_ID') con_id,sys_context('USERENV','CON_NAME')
con_name,sys_context('USERENV','SESSION_USER') curr_user FROM DUAL;
```

CON_ID	CON_NAME	CURR_USER
1	CDB\$ROOT	SYS

## 3.3 启动/关闭Root容器

### 1) 启动Root容器

ORACLE instance started.

Total System Global Area 788529152 bytes

Fixed Size 8797728 bytes

Variable Size 595591648 bytes

Database Buffers 180355072 bytes

Redo Buffers 3784704 bytes

Database mounted.

Database opened.

### 2) 打开与Root容器关联的PDB

启动ROOT容器后，但不会启动与之关联的PDB，故需要手动启动。

```
SQL> SELECT con_id,NAME,open_mode FROM v$containers;
```

CON_ID	NAME	OPEN_MODE
1	CDB\$ROOT	READ WRITE
2	PDB\$SEED	READ ONLY
3	ORCLPDB	MOUNTED

```
SQL> alter pluggable database all open;
```

Pluggable database altered.

### 3) 关闭Root容器

```
SQL> shutdown immediate
```

Database closed.

Database dismounted.  
ORACLE instance shut down.

### 3.4 创建公共用户

在插件环境中，有两种类型的用户，分别是本地用户和公共用户。本地用户是在可插拔数据库中创建的普通用户，对其的管理和非容器数据库的管理相同；公共用户是Oracle 12c中的一个新概念，它只属于可插拔数据库环境，公共用户是一个存在于root容器和每个可插拔数据库中的用户，这种类型的用户必须最先在root容器创建，并在所有现有的可插拔数据库以及未来创建的任何可插拔数据库中自动创建。

SYS和SYSTEM是Oracle在可插拔环境创建的公共用户。

公共用户的创建必须以C##或c##开头，例如：

```
[oracle@strong ~]$ sqlplus / as sysdba
```

```
SQL*Plus: Release 12.2.0.1.0 Production on Mon Aug 6 16:20:56 2018
```

```
Copyright (c) 1982, 2016, Oracle. All rights reserved.
```

```
Connected to:
```

```
Oracle Database 12c Enterprise Edition Release 12.2.0.1.0 - 64bit Production
```

```
SQL> create user c##stu identified by stu;
```

```
User created.
```

### 3.5 创建公共角色

公共角色的创建必须以C##或C##开头，例如：

```
SQL> conn / as sysdba
```

```
Connected.
```

```
SQL> create role c##select container=all;
```

```
Role created.
```

```
SQL> grant create session , select any table to c##select;
```

```
Grant succeeded.
```

```
SQL> grant create session , select any table to c##select container=all;
```

Grant succeeded.

```
SQL> grant c##select to c##stu container=all;
```

Grant succeeded.

### 3.6 报告容器空间

```
WITH x AS
(SELECT c1.con_id,
       cf1.tablespace_name,
       SUM(cf1.bytes) / 1024 / 1024 fsm
 FROM cdb_free_space cf1,
       v$containers c1
 WHERE cf1.con_id = c1.con_id
 GROUP BY c1.con_id,
          cf1.tablespace_name),
y AS
(SELECT c2.con_id,
       cd.tablespace_name,
       SUM(cd.bytes) / 1024 / 1024 apm
 FROM cdb_data_files cd,
       v$containers c2
 WHERE cd.con_id = c2.con_id
 GROUP BY c2.con_id,
          cd.tablespace_name)
SELECT x.con_id,
       v.name con_name,
       x.tablespace_name,
       x.fsm free,
       y.apm alloc
 FROM x,
       y,
       v$containers v
 WHERE x.con_id = y.con_id
       AND x.tablespace_name = y.tablespace_name
       AND v.con_id = y.con_id
UNION
SELECT vc2.con_id,
       vc2.name,
       tf.tablespace_name,
       NULL,
       SUM(tf.bytes) / 1024 / 1024
```

```
FROM v$containers vc2,  
     cdb_temp_files tf  
WHERE vc2.con_id = tf.con_id  
GROUP BY vc2.con_id,  
         vc2.name,  
         tf.tablespace_name  
ORDER BY 1,  
        2;
```

### 3.7 切换容器

```
SQL> alter session set container=orclpdb;
```

Session altered.

```
SQL> show con_name
```

```
CON_NAME  
-----
```

```
ORCLPDB
```

```
SQL> alter session set container=cdb$root;
```

Session altered.

```
SQL> show con_name
```

```
CON_NAME  
-----
```

```
CDB$ROOT
```

## 4 创建可插拔数据库PDB

### 4.1 克隆种子数据库

创建可插拔数据库的第一种方法是克隆种子数据库，是利用Create Pluggable Database语句通过拷贝种子数据库的数据文件来创建可插拔数据库，需要以SYS用户连接到Root容器。

```
SQL> conn / as sysdba
```

Connected.

```
SQL> create pluggable database salespdb admin user salesadm identified by system  
file_name_convert=  
('/u01/app/oracle/oradata/orcl/pdbseed/', '/u01/app/oracle/oradata/orcl/salespdb/');
```

Pluggable database created.

## 4.2 克隆已存在的可插拔数据库

创建可插拔数据库的第二种方法是克隆已存在的可插拔数据库，可以通过本地或远端的方式创建可插拔数据库，若从远端数据库克隆，则需要创建DBLink。

```
SQL> conn / as sysdba
```

Connected.

```
SQL> alter pluggable database salespdb close immediate;
```

Pluggable database altered.

```
SQL> alter pluggable database salespdb open read only;
```

Pluggable database altered.

```
SQL> create pluggable database salespdb2 from salespdb file_name_convert=
('/u01/app/oracle/oradata/orcl/salespdb','/home/oracle/pdbs/salespdb2');
```

Pluggable database created.

## 4.3 从非容器数据库克隆

创建可插拔数据库的第三种方法是将non\_CDB数据库转换为可插拔数据库。

1) 将non-CDB置为只读模式

```
SQL> startup mount
```

ORACLE instance started.

Total System Global Area 788529152 bytes

Fixed Size 8625656 bytes

Variable Size 633340424 bytes

Database Buffers 142606336 bytes

Redo Buffers 3956736 bytes

Database mounted.

```
SQL> alter database open read only;
```

Database altered.

2) 利用DBMS\_PDB创建XML文件，该文件用于描述non-CDB的结构

```
SQL> exec dbms_pdb.describe(pdb_descr_file => '/home/oracle/ncdb.xml');
```

PL/SQL procedure successfully completed.

### 3) 关闭non-CDB数据库

```
SQL> shutdown immediate
Database closed.
Database dismounted.
ORACLE instance shut down.
```

### 4) 连接CDB数据库

```
[oracle@strong ~]$ export ORACLE_SID=db01
[oracle@strong ~]$ sqlplus /nolog
```

```
SQL*Plus: Release 12.2.0.1.0 Production on Mon Aug 6 21:34:57 2018
```

Copyright (c) 1982, 2016, Oracle. All rights reserved.

```
SQL> conn / as sysdba
Connected to an idle instance.
SQL> startup
ORACLE instance started.
```

```
Total System Global Area 788529152 bytes
Fixed Size          8797728 bytes
Variable Size       624951776 bytes
Database Buffers   150994944 bytes
Redo Buffers        3784704 bytes
Database mounted.
Database opened.
```

### 5) 检查兼容性 (可选)

```
DECLARE
  hold_var BOOLEAN;
BEGIN
  hold_var := DBMS_PDB.CHECK_PLUG_COMPATIBILITY(pdb_descr_file => '/home/oracle/ncdb.xml');
  IF hold_var THEN
    dbms_output.put_line('YES');
  ELSE
```

```
    dbms_output.put_line('NO');
  END IF;
END;
```

如果返回值为YES，说明没有兼容性问题，如果为NO，则说明可插拔数据库兼容性有问题，可通过视图 `pdb_plug_in_violations` 查看详细信息。

#### 6) 利用non-CDB创建可插拔数据库

```
SQL> create pluggable database orclpdb using '/home/oracle/ncdb.xml' copy file_name_convert=
('/u01/app/oracle/oradata/orcl/', '/u01/app/oracle/oradata/db01/orclpdb/');
```

Pluggable database created.

#### 7) 以SYS用户连接刚创建的PDB数据库，并执行脚本

```
[oracle@strong ~]$ sqlplus /nolog
```

```
SQL*Plus: Release 12.2.0.1.0 Production on Mon Aug 6 21:58:28 2018
```

```
Copyright (c) 1982, 2016, Oracle. All rights reserved.
```

```
SQL> conn sys/system@192.168.56.102:1521/orclpdb as sysdba
```

```
Connected.
```

```
SQL> @?/rdbms/admin/noncdb_to_pdb.sql
```

该脚本必须在PDB第一次打开之前执行。

## 4.4 从容器数据库拔掉可插拔数据库

创建可插拔数据库的第四种方法是将PDB拔掉，然后插入另外的容器数据库中，拔掉会产生描述PDB的XML文件，该文件用于将其插入其他CDB容器。

#### 1) 以SYS用户连接容器，关闭PDB

```
SQL> conn / as sysdba
```

```
Connected.
```

```
SQL> alter pluggable database salespdb2 close immediate;
```

```
Pluggable database altered.
```

#### 2) 拔掉PDB

```
SQL> alter pluggable database salespdb2 unplug into '/home/oracle/pdbs/salespdb2/salespdb2.xml';
```

Pluggable database altered.

XML包含PDB的元数据信息，PDB拔掉后，在插上原来CDB之前必须先删掉，才可以插入原CDB。

### 3) 删除PDB

```
SQL> drop pluggable database salespdb2 keep datafiles;
```

Pluggable database dropped.

## 4.5 插上已拔掉的可插拔数据库

创建可插拔数据库的第五种方法是将从其它容器拔掉的PDB插入新的容器中，在插入之前，必须检查兼容性（endianness），可以使用DBMS\_PDB包进行检查。

### 1) 检查兼容性

```
DECLARE
  hold_var BOOLEAN;
BEGIN
  hold_var := dbms_pdb.check_plug_compatibility(pdb_descr_file =>
'/home/oracle/pdbs/salespdb2/salespdb2.xml');
  IF hold_var
  THEN
    dbms_output.put_line('YES');
  ELSE
    dbms_output.put_line('NO');
  END IF;
END;
```

### 2) 插入PDB

```
SQL> conn / as sysdba
```

Connected.

```
SQL> create pluggable database salespdb2 using '/home/oracle/pdbs/salespdb2/salespdb2.xml'
nocopy tempfile reuse;
```

Pluggable database created.

### 3) 打开PDB

```
SQL> alter pluggable database salespdb2 open;
```

Pluggable database altered.

## 4.6 使用DBCA创建可插拔数据库

创建可插拔数据库的第六种方法是使用DBCA工具，可以使用图形界面方式，也可以使用静默方式，这里使用静默方式演示：

```
[oracle@strong ~]$ dbca -silent -createPluggableDatabase -sourceDB orcl -pdbName hrpdb -
createPDBFrom DEFAULT -pdbAdminUserName pdbadmin -pdbAdminPassword system -
pdbDatafileDestination /home/oracle/pdbs/hrpdb
Creating Pluggable Database
2% complete
6% complete
11% complete
20% complete
46% complete
Completing Pluggable Database Creation
53% complete
Executing Post Configuration Actions
100% complete
Look at the log file "/u01/app/oracle/cfgtoollogs/dbca/orcl/hrpdb/orcl.log" for further details.
```

可通过上面的日志查看创建过程的信息。

## 4.7 检查可插拔数据库的状态

1) 查看所有可插拔数据库的状态

```
SQL> SELECT pdb_id,pdb_name,status FROM cdb_pdbs;
```

PDB_ID	PDB_NAME	STATUS
3	ORCLPDB	NORMAL
2	PDB\$SEED	NORMAL
4	SALESPDB	NORMAL
6	HRPDB	NORMAL
5	SALESPDB2	NORMAL

2) 查看可插拔数据库的打开/关闭状态

```
SQL> SELECT con_id,name,open_mode FROM v$pdb;
```

CON_ID	NAME	OPEN_MODE
2	PDB\$SEED	READ ONLY
3	ORCLPDB	READ WRITE
4	SALESPDB	READ ONLY
5	SALESPDB2	READ WRITE
6	HRPDB	READ WRITE

## 5 管理可插拔数据库PDB

### 5.1 连接PDB

1) 本地方式

```
SQL> conn / as sysdba
```

Connected.

```
SQL> alter session set container=orclpdb;
```

Session altered.

```
SQL> show con_name;
```

```
CON_NAME
-----
ORCLPDB
```

2) 网络方式

```
SQL> conn sys/system@strong.oracle.com:1521/salespdb as sysdba
```

Connected.

```
SQL> show con_name
```

```
CON_NAME
-----
SALESPDB
```

### 5.2 管理PDB的监听

如果启动一个默认监听（不使用listener.ora文件），那么PMON后台进程会自动将所有数据库（包括PDB数据库）注册为服务；如果使用了listener.ora文件，则监听器会将该文件中出现的服务名进行静态注册。

默认情况下，PDB注册的服务名与其数据库名字相同。可以SYS用户连接root容器通过如下查询来验证哪些服务正在运行：

```
SQL> conn / as sysdba
```

Connected.

```
SQL> select name, network_name, pdb from v$services order by pdb, name;
```

NAME	NETWORK_NAME	PDB
-----	-----	-----
SYS\$BACKGROUND		CDB\$ROOT
SYS\$USERS		CDB\$ROOT
orcl	orcl	CDB\$ROOT
orclXDB	orclXDB	CDB\$ROOT
hrpdb	hrpdb	HRPDB
orclpdb	orclpdb	ORCLPDB
salespdb	salespdb	SALESPDB
salespdb2	salespdb2	SALESPDB2

8 rows selected.

也可以通过lsnrctl services查看服务。

除了默认服务外，Oracle建议可以配置额外的服务，以供应用程序访问，可以使用SRVCTL命令创建，也可使用DBMS\_SERVICE包创建，这里将演示如何使用DBMS\_SERVICE创建服务：

```
SQL> conn sys/system@strong.oracle.com:1521/orclpdb as sysdba
```

Connected.

```
SQL> SELECT con_id, name, open_mode FROM v$pdbs;
```

CON_ID	NAME	OPEN_MODE
-----	-----	-----
3	ORCLPDB	READ WRITE

```
SQL> exec dbms_service.create_service(service_name=>'ORCLTEST',network_name=>'ORCLTEST');
```

PL/SQL procedure successfully completed.

```
SQL> exec dbms_service.start_service(service_name=>'ORCLTEST');
```

PL/SQL procedure successfully completed.

```
SQL> conn sys/system@strong.oracle.com:1521/orcltest as sysdba
```

Connected.

```
SQL> show con_name
```

CON\_NAME

-----

ORCLPDB

### 5.3 显示当前连接的PDB

#### 1) Show命令

```
SQL> show con_id con_name user
```

CON\_ID

-----

3

CON\_NAME

-----

ORCLPDB

USER is "SYS"

#### 2) SQL查询

```
SQL> SELECT sys_context('USERENV','CON_ID') con_id,sys_context('USERENV','CON_NAME')
con_name,sys_context('USERENV','SESSION_USER') curr_user FROM DUAL;
```

CON_ID	CON_NAME	CURR_USER
--------	----------	-----------

-----

3	ORCLPDB	SYS
---	---------	-----

SYS\_CONTEXT除了显示以上信息外，还可以显示其他信息，例如：

```
SELECT sys_context('USERENV', 'SERVICE_NAME') AS service_name,
       sys_context('USERENV', 'DB_UNIQUE_NAME') AS db_unique_name,
       sys_context('USERENV', 'INSTANCE_NAME') AS instance_name,
       sys_context('USERENV', 'SERVER_HOST') AS server_host
FROM dual;
```

### 5.4 启动/关闭PDB

有两种方式可以启动/关闭PDB，分别为：以SYS用户连接root容器，或者以SYS用户直接连接PDB。

#### 1) 连接root容器

```
SQL> conn / as sysdba
```

Connected.

```
SQL> alter pluggable database salespdb close immediate ;
```

Pluggable database altered.

```
SQL> alter pluggable database all close immediate;
```

Pluggable database altered.

```
SQL> alter pluggable database orclpdb open;
```

Pluggable database altered.

```
SQL> startup pluggable database hrpdb open read only;
```

Pluggable Database opened.

```
SQL> alter pluggable database all close immediate;
```

Pluggable database altered.

```
SQL> alter pluggable database all open;
```

Pluggable database altered.

## 2) 连接PDB

```
SQL> conn sys/system@strong.oracle.com:1521/orclpdb as sysdba
```

Connected.

```
SQL> shutdown immediate
```

Pluggable Database closed.

```
SQL>
```

```
SQL> startup
```

Pluggable Database opened.

## 5.5 修改PDB初始化参数

Oracle允许以特权用户连接到PDB时修改一些初始化参数，可以通过以下查询查看这些参数：

```
SELECT * FROM v$parameter t WHERE t.ispdb_modifiable = 'TRUE';
```

当连接到某个PDB时，对初始化参数的修改只会影响直接连接的PDB，不会影响root容器和其它PDB，例如：

```
SQL> conn sys/system@strong.oracle.com:1521/orclpdb as sysdba
```

Connected.

```
SQL> alter system set open_cursors=200;
```

System altered.

| 该修改只对orclpdb有效，并在数据库重启后保持不变。

```
SQL> conn / as sysdba
```

```
Connected.
```

```
SQL> show parameter open_cursors;
```

NAME	TYPE	VALUE
open_cursors	integer	300

## 5.6 重命名PDB

有时，可能需要重命名PDB，例如，数据库创建时可能命名错误，或者可能不再使用，并希望将\_OLD附加到它的名称中，下面演示如何对PDB进行重命名。

1) 重命名PDB，首先以SYSDBA连接

```
SQL> conn sys/system@strong.oracle.com:1521/salespdb2 as sysdba
```

```
Connected.
```

2) 关闭PDB，以restrict模式启动

```
SQL> shutdown immediate
```

```
Pluggable Database closed.
```

```
SQL> startup restrict
```

```
Pluggable Database opened.
```

3) 重命名PDB

```
SQL> alter pluggable database salespdb2 rename global_name to salespdb2_old;
```

```
Pluggable database altered.
```

```
SQL> show con_name
```

CON_NAME
SALESPDB2_OLD

## 5.7 限制PDB所占用的空间

1) 以SYS用户登录PDB

```
SQL> conn sys/system@strong.oracle.com:1521/orclpdb as sysdba
Connected.
```

2) 进行空间限制

```
SQL> alter pluggable database orclpdb storage(maxsize 10G);
```

```
Pluggable database altered.
```

## 5.8 查看PDB历史信息

通过查询数据字典CDB\_PDB\_HISTORY可以查看PDB的历史信息:

```
SQL> SELECT db_name,
           con_id,
           pdb_name,
           operation,
           op_timestamp,
           cloned_from_pdb_name
FROM cdb_pdb_history
WHERE con_id > 2
ORDER BY con_id;
```

DB_NAME	CON_ID	PDB_NAME	OPERATION	OP_TIMESTAMP	CLONED_FROM_PDB_NAME
SEEDDATA	3	PDB\$SEED	UNPLUG	2017-01-26 15:30:11	
ORCL	3	ORCLPDB	CREATE	2018-08-06 15:20:45	PDB\$SEED
ORCL	3	PDB\$SEED	PLUG	2018-08-06 15:05:45	PDB\$SEED
SEEDDATA	4	PDB\$SEED	UNPLUG	2017-01-26 15:30:11	
ORCL	4	SALESPDB	CREATE	2018-08-06 17:32:29	PDB\$SEED
ORCL	4	PDB\$SEED	PLUG	2018-08-06 15:05:45	PDB\$SEED
SEEDDATA	6	PDB\$SEED	UNPLUG	2017-01-26 15:30:11	
ORCL	6	HRPDB	CREATE	2018-08-07 10:07:07	PDB\$SEED
ORCL	6	PDB\$SEED	PLUG	2018-08-06 15:05:45	PDB\$SEED

```
9 rows selected.
```

## 5.9 删除PDB

1) 以SYS用户连接root容器，并关闭PDB

```
SQL> conn / as sysdba
```

```
Connected.
```

```
SQL> alter pluggable database salespdb2_old close immediate;
```

```
Pluggable database altered.
```

## 2) 删除PDB及其数据文件

```
SQL> drop pluggable database salespdb2_old including datafiles;
```

```
Pluggable database dropped.
```

不加 including datafiles则表示仅仅删除数据库，数据文件仍在，可以将其插入其他CDB。